

# Installation guide [AMI APTIO V]

## Installation


The instructions below are generic. If you want to add a module, follow the same steps, but substitute a different name in those places where *italic text* is used.

### Manual installation


1. Move *LogOnDxe* directory to AmiModulePkg
2. Add the path to *LogOnDxe.cif* to your project .veb file, e. g.:  
`" AmiModulePkg\LogOnDxe\LogOnDxe.cif" = Private`
3. Add the path to *LogOnDxe.sdl* to your project .ldl file, e. g.:  
`AmiModulePkg\LogOnDxe\LogOnDxe.sdl\`

### Installation via VisualBios (based on version 7.19.0561)

1. Open your project (File -> Open Project). The project format is .veb.
2. Open the menu for adding components to the project (Project -> Add -> Component...).



3. In the menu that appears, click on the "Have disk..." button and select *LogOnDxe* directory.



4. Click on "eModule" in the "Category" column. Check the *LogOnDxe* checkbox, then press the "Select" button.

## Select Components

Category	Name
eModule	<input checked="" type="checkbox"/> LogOnDxeBinary

☒ Show details

Версия #4

Владимир Мороз создал 10 October 2022 12:52:23

Александр Гончаров обновил 26 October 2022 11:01:42